



This tutorial will guide you through the process of installing the Tradunity Copy Trading on your MT4 software

Contents

Step 1 – Open A Broker Account.....	2
Step 2 - Download and install MT4 on a VPS	2
Step 3 – Download the Copy Trading Software	4
Step 4 – Install the Forex Copier Remote Receiver.....	4
Step 5 – Set up your Forex Copier Remote Receiver	5
Step 6 – Verify the Terminal to be ready to receive trades.....	7
Step 7 – Show all symbols in your MT4	8
Step 8 – Make sure your copier is set to copy the trades proportionally with your account	8
Step 10 – If needed, map your symbols.....	9
Final Checklist	11
Video tutorial	12
Troubleshooting.....	12

Step 1 – Open A Broker Account

You will need to create a broker account. Any reliable broker which offers standard accounts and MT4 trading should work.

If you don't have a broker already, we recommend to open an account on [IC Markets](#). It is a regulated broker with good reputation which is used by Tradunity for the Master Account.

You will need a standard account with 1:100 leverage.

When asked about an Introducing Broker, you can place the 7995 id, which is our affiliate code. By doing this, you will help our project further, at no extra cost for you.

If IC Markets is not available for you, please visit our page <https://tradunity.com/brokers/> in order to find alternatives.

After opening your account you will need to fund it. We are using 1000USD as a starting capital, and this sum allows us to follow our money management capital. You can use the same or more, but if you use less, please be aware that you will increase your risk percentage.

Step 2 - Download and install MT4 on a VPS

You will need to run your broker's MT4 application on a VPS (Virtual private server)

Step 2.1 If you don't have one, set up your VPS. Below the next section

there is a video tutorial on how to set up a free VPS, with step by step instructions.

IMPORTANT

When setting up the VPS machine, remember to set the location of the VPS as close as possible to the broker's location (broker's servers).

Here are a few examples:

For IC Markets: North Virginia

For Pepperstone (international): ask pepperstone where their servers are located and

For Pepperstone UK: London

For other brokers – ask them directly where their servers are located and choose a region close to that location

Video instructions:

<https://www.youtube.com/watch?v=ehBPNUIFpxU>

Note: the video was made originally for users of our robot, so it also describes how to copy the robot. You will skip that step.

Step 2.2 Download and install your MT4 software on a VPS

Please note that this video also shows you how to install our EA First Robot. For more information on our Trading Robot and how it can greatly improve your trading, please visit this page :

<https://tradunity.com/members-ea-first-pro/>

Step 2.3 Turn off Automatic Updates on your VPS to prevent it from restarting and do manual updates instead.

Instructions on how to turn off automatic updates:
https://www.youtube.com/watch?v=GQyL1_UvOkU

Step 3 – Download the Copy Trading Software


You will have to download the Copy Trading application, and then copy it to your VPS machine. You can download the application here:

<https://www.forexcopier.com/Download/DownloadLinkRemoteReceiver>


To move the application to your VPS machine, just go to your newly downloaded application, right click on it then select copy, and then go to your VPS machine and paste it on your desktop.

Step 4 – Install the Forex Copier Remote Receiver

Launch the installer on your VPS and click on “I Agree”




Now click on “Install”, wait for the installer to finish and then close the window.




Step 5 – Set up your Forex Copier Remote Receiver


Once the installation is finished, a new icon will appear on your desktop



Make sure your MT4 application is opened. And then launch the application. A new window will open, click “OK”




Now you will have to enter your email address you provided, and enter the password you have received after you signed up for Copy Trading service. Please note that for the time being it may take up to 24h to get the email or in case you have registered during the weekend, up to 48h.




Once you have inputted the credentials, click on Register.

Now select your MT Folder and click Save:




In this case you can see it's Oanda, but it can be IC Markets, or Pepperstone, or the broker you signed up with.

Once you clicked Save, a window will open, and select Yes




Step 6 – Verify the Terminal to be ready to receive trades

Once the application is relaunched, you will see this window:




Click on Fix, and your window will now look like this:



If the window still displays error, sometimes you need to press Fix a several times, and the window will be green.


Step 7 – Show all symbols in your MT4

Go to your MT4 application, navigate to the Market Watch panel, right click on the blank/white area, and select Show All (symbols)




Step 8 – Make sure your copier is set to copy the trades proportionally with your account

Open again the Copy Trading application, go to options and then select Terminal Settings



Go to the first tab Lot/Risk management, select “ Use custom lot size”.

Make sure that “Proportional lot based on Source/Receiver Equity ratio” , and that the “ And multiply the result is box is ticked, and that the value is set at “1.00” , as shown below:



Step 10 – If needed, map your symbols

Some brokers and some types of broker accounts use different non standard symbols. Usually a suffix is applied to the Symbol name, such as “.r”, “.r”, “.”, “_” etc

If your account uses these symbols, you will need to help the receiver map the symbols of the incoming orders to match your symbols.

For this, while the Terminal Options the window is still open (shown in picture above), go to the last tab (Advanced settings) and map your symbols.

You will find options to add suffixes, prefixes and special symbols as well.

Make sure to map the ones your broker instructed you to use.

For example, for Pepperstone UK European customers, for ECN accounts, the suffix “.r” is used. Thus, EURUSD becomes EURUSD.r

The example is shown in the image below:

Account setup

Configuration

It is not recommended to change these settings.

INX = S&P 500 = S&P500 = SP 500 = SP500
US30 = DJI = DJIA = Dow
NAS100 = NASDAQ = NASDAQ 100 = NASDAQ100
GER30 = DAX
UK 100 = UK100 = FTSE 100 = FTSE = FTSE100

Allow auto adjusting symbol names ?

Manual symbol name management
(use these options only if Copier cannot adjust symbol names automatically)

Add this **prefix** to symbol name of copied orders: ?

Add this **suffix** to symbol name of copied orders: .r ?

Show info labels on chart ?

Write advanced logs ?

Default settings < Prev Next > Save and finish

Forex Copier Remote Receiver Configuration

In your case you will need to check with your broker to see if any symbol is different and make the mapping accordingly.

Final Checklist

Here is the final checklist you should have in order to make sure your copier works properly

- ✓ Open a broker account and run the MT4 on a VPS 24/7
- ✓ Turn off the automatic updates of the VPS, do manual maintenance instead
- ✓ Install the Trading Copier Receiver application and set it up to work on your MT4
- ✓ Register with your email and password received via email
- ✓ Make sure the General, Connection and Terminal are all green (press fix otherwise)
- ✓ In MT4, make sure the smiley face next to ReceiverEA is smiling
- ✓ You should have only have one chart open with the ReceiverEA attached to it
- ✓ In the market watch panel, make sure “Show all Symbols” is selected
- ✓ Copy the trades proportionally: “Proportional lot based on Source/Receiver Equity ratio” has to be selected with a value of 1
- ✓ (Optional) – if needed, make sure to map your symbols to match those of your broker
- ✓ Have the Receiver application and the MT4 running all the time

Done! If you’ve done everything as shown above in all the steps, your Copy Trading application is now working properly, and your MT4 application should look like this:



Video tutorial

This tutorial in video format is available here:

<https://youtu.be/MHAtS1IMFKU>

Troubleshooting

In case any issues arise, they should be marked in red on the chart, below the yellow lines. Follow the instructions of the red messages in order to fix the issues, and in case the issue repeats itself, don't hesitate to open a support ticket on <https://tradunity.com> or to ask us on our chat groups.